



BOW TIE PATTERN AND GUIDANCE

HOW TO
PUT YOUR DESIGN INTO A FULLPRINT PATTERN





HOW TO

PUT your design into a fullprint pattern

Open the pattern file which you downloaded from the product page (please only use the pattern according to the size that you want to order) on Adobe Photoshop. Illustration is using Adobe Photoshop

HOW TO CREATE WOMAN SMALL SLING BAG WITH YOUR OWN DESIGN





Need your attention:

1. Please pay attention to pattern part position.
2. Black line is fabric/pattern cutting line.
3. Red mark on every corner is a sewing/ folding line



ESTIMATED SEWING PART IS ABOUT 1 - 2 Cm AFTER PATTERN LINE

MAKE SURE YOUR DESIGN NOT BE CUTED



Guidelines

HOW TO
PUT your design into a fullprint pattern


 - ESTIMATED SEWING PART
IS ABOUT 1 - 2 Cm AFTER
PATTERN LINE

MAKE SURE YOUR DESIGN
NOT BE CUTED

To avoid your design is being cutted/ destroyed, follow these steps.

1. Enlarge the area using Zoom tool [Q] at left side so you can see the red at the corner.

2. Connect the red mark and you may see the Red Area as an estimated sewing area and Green Area is the estimated your design area.





FILLING PATTERN

HOW TO

PUT your design into a fullprint pattern

Open the pattern file and your design file on Adobe Photoshop.

1. Go to Window menu on the menu bar, select Arrange then Title All Vertically (Window > Arrange > Title All Vertically)





FILLING PATTERN

HOW TO

PUT your design into a fullprint pattern

2. From your Design file, go to Select menu on menu bar then choose All (Select > All)





FILLING PATTERN

HOW TO

PUT your design into a fullprint pattern

3. Goto Edit than Copy (Edit > Copy)





FILLING PATTERN

HOW TO

PUT your design into a fullprint pattern

4. On the pattern file window, use the Magic Wand Tool (at tool bar on the left side) then left-click inside the part you want to work with





FILLING PATTERN

HOW TO

PUT your design into a fullprint pattern


5. Go to Edit from menu bar then select Paste Special and Paste Into (Edit > Paste Special > Paste Into). You may adjust the pasted image by dragging it.



FILLING PATTERN


HOW TO
PUT YOUR DESIGN INTO A FULLPRINT PATTERN

6. Before continue another part you should click **background layer** at layer list.



If layer list did not show you can easily press **F7** button on your keyboard or go to menu bar **Window > Layer**

7. You can repeat selecting part by using **Magic Wand** and after you can **Paste Special** the design until all part filled.



SAVING FILE

HOW TO PUT YOUR DESIGN INTO A FULLPRINT PATTERN

As the final step you can Save your design by clicking from the menu bar **File > Save As**

New...	Ctrl+N
Open...	Ctrl+O
Browse in Bridge...	Alt+Ctrl+O
Browse in Mini Bridge...	
Open As...	Alt+Shift+Ctrl+O
Open as Smart Object...	
Open Recent	
Close	Ctrl+W
Close All	Alt+Ctrl+W
Close and Go to Bridge...	Shift+Ctrl+W
Save	Ctrl+S
Save As...	Shift+Ctrl+S
Check In...	
Save for Web...	Alt+Shift+Ctrl+S
Revert	F12

For the file type change it to **JPG** format.

NOTE:
Minimum **Quality 8 (High)**
Please **NOT** to change **Image Size**.
Always aware of **Cutting/Sewing Part**.

